

Software Configuration Requirements

Component	Minimum system configuration	Suggested configuration
Processor	Pentium® processor	Pentium II 300 Mhz or better
Operating System	Microsoft® Windows® 95 (Version B)	Microsoft Windows 2000 All versions of Windows 2000
Memory	<ul style="list-style-type: none"> • Windows 95 or Windows 98: 16 megabytes (MB) of random access memory (RAM) • Windows NT 4.0: 32 MB of RAM , and you must be running Service Pack 3 or later • Windows 2000 or XP: 64 MB of RAM • Windows Me: 32 MB of RAM 	64 MB of RAM
Disk space	<p>100 MB of hard disk space available</p> <p>How to find out if your computer complies:</p> <ol style="list-style-type: none"> 1. Open My Computer, by double-clicking its icon on the desktop. 2. Then click the disk you want to check. 3. The amount of free space also appears in the status bar at the bottom of the screen. If you cannot see the free space, drag the right side of the window to enlarge it. 4. If the status bar is not visible, click the View menu, and then click Status Bar. 5. If you have turned on Web content in folders, you can select the disk to display the free space on the left side of the folder window. 6. You can also view the free space and other disk properties by right-clicking the disk and then clicking Properties. 	<p>500 MB of hard disk space available</p> <p>The actual disk space required to run this program is less than 10MB. The additional free disk space is recommended to avoid other performance issues on your PC. For example, your computer and the programs you use keep many temporary files on your hard disk which require varying amounts of disk space. When disk space is low computer and program performance may decrease.</p>
Monitor	<p>14" monitor; display set to 800x600/256 colors</p> <p>How to find out if your computer complies:</p> <ol style="list-style-type: none"> 1. Click the Windows® Start button and select Settings, then select Control Panel. 2. Double-click Display 3. Click the Settings tab. You'll see information about your computer's screen area. 4. Click OK to exit. 	<p>17" color monitor; display set to 1024 x 768/High Color-16 bit</p> <p>Ideally when viewing web pages you want as large a resolution as you can get. The larger the resolution, the more of a page fits on the screen. Since many web pages are too large to fit on one screen, a larger resolution allows you to see more of a page. We suggest using a resolution of 800 X 600 if you have a 14 or 15-inch monitor, and a resolution of 1024 X 768 for 17-inch and larger monitors.</p>
Browser	<p>Microsoft Internet Explorer 5.50</p> <p>How to find out if you have the right version</p> <ol style="list-style-type: none"> 1. Launch Microsoft Internet Explorer. 2. Select Help > About Internet Explorer. The version information window will display. 3. Minimum Version: 5.50 4. Click OK to exit the window 	<p>Microsoft Internet Explorer 6.0</p> <p>If your Internet Explorer version is not 5.50 or above you will need to update your Internet Explorer. For Microsoft Windows product updates go to: http://windowsupdate.microsoft.com/</p>
Web Service	<p>MSXML 4.0</p> <p>Run the install to ensure you have the right version.</p>	<p>To install MSXML 4.0 go to your eStore log in page and click the system check link. Expand the Web Services requirements in the Required Hardware and Software table and click the download link.</p>
Web Plugin	<p>Macromedia Flash Player 6.0 MX (Buyer registration only)</p> <p>Run the install to ensure you have the latest version.</p>	<p>To install the latest version of the Flash Player go to www.macromedia.com/software/downloads/</p>
Modem	<ul style="list-style-type: none"> • 56K Modem • An Internet Service Provider (ISP) 	Broadband internet connection (cable modem or DSL)*

* All Modem, DSL, cable or T1 connections must be configured by your local provider.

NOTE: These configurations are subject to change at the sole discretion of the publisher.